

```

1 #####
2 # rsnapshot.conf - rsnapshot configuration file #
3 #####
4 #
5 # PLEASE BE AWARE OF THE FOLLOWING RULES:
6 #
7 # This file requires tabs between elements
8 #
9 # Directories require a trailing slash:
10 #   right: /home/
11 #   wrong: /home
12 #
13 #####
14
15 #####
16 # CONFIG FILE VERSION #
17 #####
18
19 config_version 1.2
20
21 #####
22 # SNAPSHOT ROOT DIRECTORY #
23 #####
24
25 # All snapshots will be stored under this root directory.
26 #
27 snapshot_root /datos/backup/
28
29 # If no_create_root is enabled, rsnapshot will not automatically create the
30 # snapshot_root directory. This is particularly useful if you are backing
31 # up to removable media, such as a FireWire or USB drive.
32 #
33 #no_create_root 1
34
35 #####
36 # EXTERNAL PROGRAM DEPENDENCIES #
37 #####
38
39 # LINUX USERS: Be sure to uncomment "cmd_cp". This gives you extra features.
40 # EVERYONE ELSE: Leave "cmd_cp" commented out for compatibility.
41 #
42 # See the README file or the man page for more details.
43 #
44 cmd_cp /bin/cp
45
46 # uncomment this to use the rm program instead of the built-in perl routine.
47 #
48 cmd_rm /bin/rm
49
50 # rsync must be enabled for anything to work. This is the only command that
51 # must be enabled.
52 #
53 cmd_rsync /usr/bin/rsync
54
55 # Uncomment this to enable remote ssh backups over rsync.
56 #
57 #cmd_ssh /usr/bin/ssh
58
59 # Comment this out to disable syslog support.
60 #
61 cmd_logger /usr/bin/logger
62
63 # Uncomment this to specify the path to "du" for disk usage checks.
64 # If you have an older version of "du", you may also want to check the
65 # "du_args" parameter below.
66 #
67 #cmd_du /usr/bin/du
68
69 # Uncomment this to specify the path to rsnapshot-diff.
70 #
71 #cmd_rsnapshot_diff /usr/bin/rsnapshot-diff
72
73 # Specify the path to a script (and any optional arguments) to run right

```

```

74 # before rsnapshot syncs files
75 #
76 #cmd_preexec    /path/to/preexec/script
77
78 # Specify the path to a script (and any optional arguments) to run right
79 # after rsnapshot syncs files
80 #
81 #cmd_postexec    /path/to/postexec/script
82
83 # Paths to lvcreate, lvremove, mount and umount commands, for use with
84 # Linux LVMs.
85 #
86 #linux_lvm_cmd_lvcreate /sbin/lvcreate
87 #linux_lvm_cmd_lvremove /sbin/lvremove
88 #linux_lvm_cmd_mount    /bin/mount
89 #linux_lvm_cmd_umount    /bin/umount
90
91 #####
92 #          BACKUP INTERVALS          #
93 # Must be unique and in ascending order #
94 # i.e. hourly, daily, weekly, etc.    #
95 #####
96
97 retain    hourly  12
98 retain    daily   7
99 retain    weekly  4
100 retain    monthly 12
101
102 #####
103 #          GLOBAL OPTIONS          #
104 # All are optional, with sensible defaults #
105 #####
106
107 # Verbose level, 1 through 5.
108 # 1      Quiet          Print fatal errors only
109 # 2      Default        Print errors and warnings only
110 # 3      Verbose        Show equivalent shell commands being executed
111 # 4      Extra Verbose  Show extra verbose information
112 # 5      Debug mode     Everything
113 #
114 verbose    2
115
116 # Same as "verbose" above, but controls the amount of data sent to the
117 # logfile, if one is being used. The default is 3.
118 #
119 loglevel    3
120
121 # If you enable this, data will be written to the file you specify. The
122 # amount of data written is controlled by the "loglevel" parameter.
123 #
124 logfile /var/log/rsnapshot.log
125
126 # If enabled, rsnapshot will write a lockfile to prevent two instances
127 # from running simultaneously (and messing up the snapshot_root).
128 # If you enable this, make sure the lockfile directory is not world
129 # writable. Otherwise anyone can prevent the program from running.
130 #
131 lockfile    /var/run/rsnapshot.pid
132
133 # By default, rsnapshot check lockfile, check if PID is running
134 # and if not, consider lockfile as stale, then start
135 # Enabling this stop rsnapshot if PID in lockfile is not running
136 #
137 #stop_on_stale_lockfile    0
138
139 # Default rsync args. All rsync commands have at least these options set.
140 #
141 #rsync_short_args    -a
142 #rsync_long_args     --delete --numeric-ids --relative --delete-excluded
143
144 # ssh has no args passed by default, but you can specify some here.
145 #
146 #ssh_args    -p 22 -o BatchMode=yes

```

```
147
148 # Default arguments for the "du" program (for disk space reporting).
149 # The GNU version of "du" is preferred. See the man page for more details.
150 # If your version of "du" doesn't support the -h flag, try -k flag instead.
151 #
152 #du_args      -csh
153
154 # If this is enabled, rsync won't span filesystem partitions within a
155 # backup point. This essentially passes the -x option to rsync.
156 # The default is 0 (off).
157 #
158 #one_fs       0
159
160 # The include and exclude parameters, if enabled, simply get passed directly
161 # to rsync. If you have multiple include/exclude patterns, put each one on a
162 # separate line. Please look up the --include and --exclude options in the
163 # rsync man page for more details on how to specify file name patterns.
164 #
165 #include      ???
166 #include      ???
167 #exclude      ???
168 #exclude      ???
169
170 # The include_file and exclude_file parameters, if enabled, simply get
171 # passed directly to rsync. Please look up the --include-from and
172 # --exclude-from options in the rsync man page for more details.
173 #
174 #include_file  /path/to/include/file
175 #exclude_file  /path/to/exclude/file
176
177 # If your version of rsync supports --link-dest, consider enable this.
178 # This is the best way to support special files (FIFOs, etc) cross-platform.
179 # The default is 0 (off).
180 #
181 #link_dest     0
182
183 # When sync_first is enabled, it changes the default behaviour of rsnapshot.
184 # Normally, when rsnapshot is called with its lowest interval
185 # (i.e.: "rsnapshot hourly"), it will sync files AND rotate the lowest
186 # intervals. With sync_first enabled, "rsnapshot sync" handles the file sync,
187 # and all interval calls simply rotate files. See the man page for more
188 # details. The default is 0 (off).
189 #
190 #sync_first    0
191
192 # If enabled, rsnapshot will move the oldest directory for each interval
193 # to [interval_name].delete, then it will remove the lockfile and delete
194 # that directory just before it exits. The default is 0 (off).
195 #
196 #use_lazy_deletes  0
197
198 # Number of rsync re-tries. If you experience any network problems or
199 # network card issues that tend to cause ssh to crap-out with
200 # "Corrupted MAC on input" errors, for example, set this to a non-zero
201 # value to have the rsync operation re-tried
202 #
203 #rsync_numtries 0
204
205 # LVM parameters. Used to backup with creating lvm snapshot before backup
206 # and removing it after. This should ensure consistency of data in some special
207 # cases
208 #
209 # LVM snapshot(s) size (lvcreate --size option).
210 #
211 #linux_lvm_snapshotsizesize 100M
212
213 # Name to be used when creating the LVM logical volume snapshot(s).
214 #
215 #linux_lvm_snapshotname rsnapshot
216
217 # Path to the LVM Volume Groups.
218 #
219 #linux_lvm_vgpath    /dev
```

```
220
221 # Mount point to use to temporarily mount the snapshot(s).
222 #
223 #linux_lvm_mountpath      /path/to/mount/lvm/snapshot/during/backup
224
225 #####
226 ### BACKUP POINTS / SCRIPTS ###
227 #####
228
229 # LOCALHOST
230 backup /datos/samba/      localhost/
231 backup /backup/homes/      localhost/
232 backup /etc/               localhost/
233 #backup /usr/local/        localhost/
234 #backup /var/log/rsnapshot  localhost/
235 #backup /etc/passwd         localhost/
236 #backup /home/foo/My Documents/ localhost/
237 #backup /foo/bar/          localhost/ one_fs=1, rsync_short_args=-urltvpog
238 #backup_script /usr/local/bin/backup_pgsql.sh localhost/postgres/
239 # You must set linux_lvm_* parameters below before using lvm snapshots
240 #backup lvm://vg0/xen-home/ lvm-vg0/xen-home/
241
242 # EXAMPLE.COM
243 #backup_script /bin/date "+ backup of example.com started at %c" unused1
244 #backup root@example.com:/home/ example.com/
245 +rsync_long_args=--bwlimit=16,exclude=core
246 #backup root@example.com:/etc/ example.com/ exclude=mtab,exclude=core
247 #backup_script ssh root@example.com "mysqldump -A > /var/db/dump/mysql.sql"
248 unused2
249 #backup root@example.com:/var/db/dump/ example.com/
250 #backup_script /bin/date "+ backup of example.com ended at %c" unused9
251
252 # CVS.SOURCEFORGE.NET
253 #backup_script /usr/local/bin/backup_rsnapshot_cvsroot.sh
254 rsnapshot.cvs.sourceforge.net/
255
256 # RSYNC.SAMBA.ORG
257 #backup rsync://rsync.samba.org/rsyncftp/ rsync.samba.org/rsyncftp/
```